

Computational model of auxin-CUC interaction in the floral meristem

Shuyao Kong, Mingyuan Zhu, David Pan, Brendan Lane, Richard S. Smith, Adrienne H. K. Roeder

10/10/2023

Summary

The floral meristem is modeled using a 2D disk of cells that are growing and dividing, based on two previous models, GridAuxin and MassSpringCells. Mechanics are modeled using a mass-spring model where cell walls (springs) are pulling cell wall junctions (masses). Each cell has auxin, CUC, and PIN, that are produced, degraded, and interacting, calculated using a differential equations solver. The model is implemented in C++, and can be run inside the VLab environment¹ and the MorphoDynamX software². The model can be run either one simulation at a time, or batch-run using a python code.

The Model Folder

Within the model folder “MassSpringAuxin”:

- “specifications.txt” lists all the files within the folder to be included with the model
- “CellDisk.hpp” and “CellDisk.cpp” are the model source files, and can be edited using a text editor or IDEs such as VS Code.
- “CellDisk.mdxv” can be edited using a text editor, and contain metadata of the model, including which initial condition to use.
- “Init_blank_72cells_2023-09-07.mdxm” is the initial condition used in the model. This can be changed to another MDX mesh file.

Running the model one simulation at a time

1. Open the VLab Browser.
2. Select the oofs repository.
3. Navigate to the model, and double click on the window to open it.
4. Right click on the model icon, and select “run”. The model would now open in MDX.
5. Set the desired parameters, mainly in Process -> Model -> 01 Cell Disk and Process -> Model -> Auxin Gradient Model. If output is desired, set “Run name”, “Output directory”, and “Output frequency”.
6. Double-click Process -> Model -> 01 Cell Disk to run it. Click on the stop button to stop when desired.

Running the model in batch mode

1. Using a python code, such as the provided “create_run_20231010_demo.py”, create a run file, such as the provided “run_20231010.py”. The former file specifies the parameter combinations to be tested, while the latter file contains the commands to be fed into MDX.
2. Open the model in MDX following steps 1-4 in the previous section.

3. Under Process -> Tools -> Python -> Python Script, select the run file created in step 1 ("run_20231010.py"). The model would now run automatically.
4. Screenshots are automatically saved in "output directory/run name/Screenshots/*.jpg". Cell complex data are automatically saved in "output directory/run name/CCData/*.txt". The following data are saved in these files: Cell index (CCIndex), x and y coordinates, cell area, and auxin and CUC concentrations. Each row represents a cell.
5. In the demo, 5 simulations each of WT, *drmy1*, *cuc1*, and *drmy1 cuc1*, with growth rates 0.4, 0.8, and 1.2 were run, and the results were saved in the directory "20231010". The simulations were named as follows: "*Run_CUC Prod_SD Auxin Prod_PIN low CUC_PIN high CUC_Plasticity_Unchanging Noise_sim number_date*".

Parsing and analysis of CCData

1. The code "Parse_output_2023-10-10_demo.R" parses these data files, identifies auxin maxima, tracks them over time, and summarizes them in "RData_20231010.RData". It also plots how auxin maxima are assigned and tracked. These plots are saved in "output directory/run name/CCData/*.png".
2. The data frames in the output RData file can be analyzed as desired. For example, the provided code "Modeling_analysis_2023-10-10_demo.R" reads in the RData file and generates three plots in the "Plots" folder.

References

1. Federl, P., and Prusinkiewicz, P. (1999). Virtual laboratory: An interactive software environment for computer graphics. Proc. - Comput. Graph. Int. CGI 1999. 10.1109/CGI.1999.777921.
2. Strauss, S., Runions, A., Lane, B., Eschweiler, D., Bajpai, N., Trozzi, N., Routier-Kierzkowska, A.L., Yoshida, S., Da Silveira, S.R., Vijayan, A., et al. (2022). Using positional information to provide context for biological image analysis with MorphoGraphX 2.0. eLife 11, 1–38. 10.7554/eLife.72601.